

# The width of the text description 01 edit table is 100%, but the table exceeds the border when browsing on the mobile phone after launching the listing?

776 | 776 | 776: Wed, Jul 29, 2020 2:56 PM

The width of the text description 01 edit table is 100%, but the table exceeds the border when browsing on the mobile phone after launching the listing?

The width of the text description 01 edit table is 100%, but the table exceeds the border when browsing on the mobile phone after launching the listing?

Example

Edit a table in the text description 01, the setting of width is 100%, edit content as follows:

修改产品描述

源码 ← → [List Icons] **B** *I* U ~~Strikethrough~~ [List Icons] 字体 - 大小 - [Color Icons]

**Specification:**

Frequency	50-60Hz	50-60Hz	50-60Hz	50-60Hz	50-60Hz
Working Temperature	-20°C-65°C	-20°C-65°C	-20°C-65°C	-20°C-65°C	-20°C-65°C
Watt	3W	5W	7W	9W	12W
Replace for	30W	45W	60W	75W	100W
Light Color	Warm White (3000K-3200K)	Warm White (3000K-3200K)	Warm White (3000K-3200K)	Warm White (3000K-3200K)	Warm White (3000K-3200K)
Lumen	250lm-350lm	400lm-450lm	500lm-650lm	700lm-850lm	900lm-1100lm
Type	E27/B22/E14	E27/B22/E14	E27/B22	E27/B22	E27/B22

After launching the listing, browsing the table on the mobile phone, you will find that the table exceeds the border and is only the display part, the effect as follows:



E27



B22



E14

**Specification :**

Frequency	50-60Hz	50-60Hz	50-60
Working Temperature	-20°C-65°C	-20°C-65°C	-20
Watt	3W	5W	
Replace for	30W	45W	
Light Color	Warm White (3000K-3200K)	Warm White (3000K-3200K)	Warm (3000-3200K)
Lumen	250lm-350lm	400lm-450lm	500lm
Type	E27/B22/E14	E27/B22/E14	E
Input	AC 160V-260V	AC 160V-260V	AC 160V-260V
Size(error range:1-2cm)	4.5*4.5*8.2cm	5*5*9cm	6*6*9cm

The reason for this problem is that the text content is too long and cause the displayed content incomplete, the solution as follows:

1. Open the ' **Text Description 01** ' and click the ' **Source Code** ' on the upper left

corner of the text edit box

2. Open the source code and find the `table` in the table part inside

3. Add `word-wrap: break-word; word-break: break-all` to the `style=""` behind the table;

Click <Save> and done!

\*\*\*Fin\*\*\*

???: Holistic Tech - Wed, Jul 29, 2020 12:35 PM. ??????? 1735 ?

??URL: <https://www.soldeazy.com/support/article.php?id=776>